

# Key Management Service TCCLI Management Guide



## Copyright Notice

©2013–2023 Tencent Cloud. All rights reserved.

Copyright in this document is exclusively owned by Tencent Cloud. You must not reproduce, modify, copy or distribute in any way, in whole or in part, the contents of this document without Tencent Cloud's the prior written consent.

## Trademark Notice

 Tencent Cloud

All trademarks associated with Tencent Cloud and its services are owned by Tencent Cloud Computing (Beijing) Company Limited and its affiliated companies. Trademarks of third parties referred to in this document are owned by their respective proprietors.

## Service Statement

This document is intended to provide users with general information about Tencent Cloud's products and services only and does not form part of Tencent Cloud's terms and conditions. Tencent Cloud's products or services are subject to change. Specific products and services and the standards applicable to them are exclusively provided for in Tencent Cloud's applicable terms and conditions.

# Contents

## TCCLI Management Guide

Operation Overview

Creating Key

Viewing keys

Editing Key

Enabling/Disabling Key

Key Rotation

Encryption and Decryption

Asymmetric Key Decryption

Deleting Key

Archive Key

# TCCLI Management Guide

## Operation Overview

Last updated: 2023-08-24 11:42:45

You can call KMS TCCLI to manage your keys, such as creating/editing/rotating a key and viewing the key ID list.

Operations can be performed using Tencent Cloud's [Command Line Tool TCCLI](#), and subsequently, you can call it using any supported programming language.

| Action                                    | Note  |
|---|---|
| <a href="#">Create a Key</a>              | Describes how to call TCCLI to create a key   |
| <a href="#">View a Key</a>                | Provides an example of how to call TCCLI to view the key ID and detailed information. |
| <a href="#">Edit a Key</a>                | Describes how to call TCCLI to edit a key   |
| <a href="#">Enable/Disable a Key</a>      | Describes how to call TCCLI to enable/disable a key.                                  |
| <a href="#">Key Rotation</a>              | Describes how to call TCCLI to rotate a key   |
| <a href="#">Encryption and Decryption</a> | Describes how to call TCCLI for encryption and decryption                             |
| <a href="#">Delete a Key</a>              | Describes how to call TCCLI to delete a key   |
| <a href="#">Key Archiving</a>             | Describes how to call TCCLI to enable/disable key archiving.                          |

# Creating Key

Last updated: 2023-08-24 17:26:18

## Overview

The CreateKey API can be called to create a customer master key (CMK) used for DEK management. The CMK can be used in other APIs to create DEKs, perform encryption and decryption, and do more.

The Alias is a required parameter in this API operation. You can refer to the CreateKey API documentation to add additional descriptions to the CMK.

This example uses Tencent Cloud's [Command Line Tool TCCLI](#). You can use any supported programming language for subsequent calls.

## Sample

This example shows you how to create a key named `test-gz01` in Guangzhou region with the description `this is test for gz key`.

## Input

```
tccli kms CreateKey --region ap-guangzhou --Alias test-gz01 --Description 'this is test for g
```

## Output

After creation, the key will be enabled by default, with the key rotation feature disabled.

```
{
  "KeyId": "6xxxxxxx-xxxx-xxxx-xxxx-5xxxxxxxxxc09",
  "Description": "this is test for gz key",
  "Alias": "test-gz01",
  "KeyUsage": "ENCRYPT_DECRYPT",
  "RequestId": "994bbd90-7c8e-4522-85f2-c712da23f863",
  "KeyState": "Enabled",
  "CreateTime": 1571903621
}
```

# Viewing keys

Last updated: 2023-08-24 17:29:34

## Overview

| API         | API Description  | Note   |
|-------------|--|--|
| ListKeys    | List the key information (KeyId) under the account   | This API operation has no required parameters. For more information, see the <a href="#">ListKeys</a> interface.                       |
| DescribeKey | View the detailed information of a specified Customer Master Key (CMK), including the CMK name, ID, status, region, and other key details. | The KeyId for this API operation is a required parameter. For more details, please refer to the <a href="#">DescribeKey</a> interface. |

This example uses Tencent Cloud's [Command Line Tool TCCLI](#). You can use any supported programming language for subsequent calls.

## Sample

### Viewing Key ID List Example

This example describes how to view the information of the first five KeyIds in Guangzhou region.

### Input

```
tccli kms ListKeys --region ap-guangzhou --Limit 5
```

### Output

```
{
  "Keys": [
    {
      "KeyId": "6xxxxxxxx-xxxx-xxxx-xxxx-5xxxxxxxxc09"
    },
    {
      "KeyId": "6xxxxxxxx-xxxx-xxxx-xxxx-5xxxxxxxxc09"
    },
    {
      "KeyId": "6xxxxxxxx-xxxx-xxxx-xxxx-5xxxxxxxxc09"
    }
  ],
}
```

```
{
  "KeyId": "6xxxxxxx-xxxx-xxxx-xxxx-5xxxxxxxxxc09"
},
{
  "KeyId": "6xxxxxxx-xxxx-xxxx-xxxx-5xxxxxxxxxc09"
}
],
"TotalCount": 114,
"RequestId": "afaaeb5e-c97d-4726-8012-6ae337d62928"
}
```

## Viewing Key ID Details Example

This example describes how to view the details of the specified CMK.

### Input

```
tccli kms DescribeKey --region ap-guangzhou --KeyId 521xxxxx-xxxx-xxxx-xxxx-52xxxxd4
```

### Output

If the API is successfully executed, the details of the CMK will be returned.

```
{
  "KeyMetadata": {
    "KeyId": "6xxxxxxx-xxxx-xxxx-xxxx-5xxxxxxxxxc09",
    "Description": "this is test for gz key",
    "CreatorUin": 10xxxxxxxxxx,
    "KeyRotationEnabled": false,
    "NextRotateTime": 1603439621,
    "CreateTime": 1571903621,
    "Alias": "test-gz01",
    "KeyUsage": "ENCRYPT_DECRYPT",
    "DeletionDate": 0,
    "KeyState": "Enabled",
    "Type": 4,
    "Owner": "user"
  },
  "RequestId": "608f514c-3279-44ea-8e4c-c00b69e3521c"
}
```

# Editing Key

Last updated: 2023-08-24 15:50:35

## Overview

The operations of renaming a key and modifying key description involve the following two functions:

| API                  | API Description        | Note   |
|----------------------|------------------------|--|
| UpdateAlias          | Modify Key Name        | The KeyId and Alias are mandatory parameters for this API operation. For more details, please refer to the <a href="#">UpdateAlias</a> interface documentation.                |
| UpdateKeyDescription | Modify Key Description | The KeyId and Description are mandatory parameters for this API operation. For more details, please refer to the <a href="#">UpdateKeyDescription</a> interface documentation. |

This example uses Tencent Cloud's [Command Line Tool TCCLI](#). You can use any supported programming language for subsequent calls.

## Sample

### Example of Renaming a Key

#### Input

```
tccli kms UpdateAlias --region ap-guangzhou --KeyId 52xxxx-xxxx-xxxx-xxxx-5xxxx4 --Ali
```

#### Output

If the modification is successful, the following information will be returned.

```
{  
  "RequestId": "489a4274-0b81-4db7-8160-542c5c5bed68"  
}
```

### Modifying Key Description Example

#### Input

```
tccli kms UpdateKeyDescription --region ap-guangzhou --KeyId 5xxxxx-xxxx-xxxx-xxxx-5:
```

## Output

If the modification is successful, the following information will be returned.

```
{  
  "RequestId": "31134207-5de8-44f2-8c00-8bd0e88f95a6"  
}
```

# Enabling/Disabling Key

Last updated: 2023-08-24 15:51:06

## Overview

The operations of enabling and disabling a key involve the following two APIs:

| API        | API Description                      | Note  |
|------------|--------------------------------------|---|
| EnableKey  | Enable the Customer Master Key (CMK) | The KeyId is a required parameter for this API operation. For more details, please refer to the <a href="#">EnableKey</a> interface documentation.  |
| DisableKey | Disable Master Key                   | The KeyId is a required parameter for this API operation. For more details, please refer to the <a href="#">DisableKey</a> interface documentation. |

This example uses Tencent Cloud's [Command Line Tool TCCLI](#). You can use any supported programming language for subsequent calls.

## Sample

### Enable Key Example

#### Input

```
tccli kms EnableKey --region ap-guangzhou --KeyId 5xxxxx-xxxx-xxxx-xxxx-52xxxxx4
```

#### Output

If the key is successfully enabled, the following request will be returned.

```
{
  "RequestId": "6b2187b0-f40a-46d0-8065-2434afc54619"
}
```

### Disable Key Example

#### Input

```
tccli kms DisableKey --region ap-guangzhou --KeyId 5xxxxx-xxxx-xxxx-xxxx-52xxxxx4
```

## Output

If the key is successfully disabled, the following request will be returned.

```
{  
  "RequestId": "e5674638-1466-4607-a3ea-b60d30f4e5e3"  
}
```

# Key Rotation

Last updated: 2023-08-24 15:51:37

## Overview

The key rotation feature involves three APIs:

| API                  | API Description          | Note  |
|----------------------|--------------------------|---|
| GetKeyRotationStatus | View key rotation status | The KeyId is a required parameter for this API operation. For more details, please refer to the <a href="#">GetKeyRotationStatus</a> interface documentation. |
| Enable Key Rotation  | Enable Key Rotation      | The KeyId is a required parameter for this API operation. For more details, please refer to the <a href="#">EnableKeyRotation</a> interface documentation.    |
| Disable Key Rotation | Disable Key Rotation     | The KeyId is a required parameter for this API operation. For more details, please refer to the <a href="#">DisableKeyRotation</a> interface documentation.   |

This example uses Tencent Cloud's [Command Line Tool TCCLI](#). You can use any supported programming language for subsequent calls.

## Sample

### View Key Rotation Status Example

#### Input

```
tccli kms GetKeyRotationStatus --region ap-guangzhou --KeyId 5xxxxx-xxxx-xxxx-xxxx-52
```

#### Output

If the API is called successfully, the key rotation status of the CMK will be returned.

```
{
  "KeyRotationEnabled": false,
  "RequestId": "e1432224-4dc2-48da-a8e8-e84d30afd9ef"
}
```

### Enable Key Rotation Example

## Input

```
tccli kms EnableKeyRotation --region ap-guangzhou --KeyId 5xxxxx-xxxx-xxxx-xxxx-52xx:
```

## Output

If the feature is disabled normally, the request information as shown below will be returned.

```
{  
  "RequestId": "4e0fa96f-e86e-4517-af27-3dfe6e5b2a72"  
}
```

## Disable Key Rotation Example

### Input

```
tccli kms DisableKeyRotation --region ap-guangzhou --KeyId 5xxxxx-xxxx-xxxx-xxxx-52xx
```

### Output

If the feature is disabled normally, the request information as shown below will be returned.

```
{  
  "RequestId": "c8b73c8b-1ee5-4b23-b800-7cccc58e7ffb"  
}
```

# Encryption and Decryption

Last updated: 2023-08-24 15:52:02

## Overview

The online encryption and decryption operations involve two APIs:

| API     | API Description | Note  |
|---------|-----------------|---|
| Encrypt | Encrypt         | The KeyId and Plaintext are mandatory parameters for this API operation. For more details, please refer to the <a href="#">Encrypt</a> interface documentation. |
| Decrypt | Decrypt         | The CiphertextBlob is a required parameter for this API operation. For more details, please refer to the <a href="#">Decrypt</a> interface documentation.       |

## Encryption

Encrypt is used to encrypt user data, with a maximum data size of 4KB for any data, suitable for encrypting database passwords, RSA Keys, or other small sensitive information. For application data encryption, it is recommended to use the DEK generated by [GenerateDataKey](#) for local data encryption and decryption operations.

This example uses Tencent Cloud's [Command Line Tool TCCLI](#). You can use any supported programming language for subsequent calls.

## Sample

### Encryption Example

When using TCCLI to call the encryption interface, you need to perform Base64 encoding on the plaintext data. This example uses the text "This example is used for testing."

### Input

```
tccli kms Encrypt --KeyId 6xxxxxx-xxxx-xxxx-xxxx-5xxxxxxxxxx5 --Plaintext "VGhpcyBleGI
```

### Output

If the execution is successful, the ciphertext and the CMK ID used to encrypt the plaintext will be returned, of which the ciphertext will be used for subsequent decryption operations.

```
{
  "KeyId": "6xxxxxx-xxxx-xxxx-xxxx-5xxxxxxxxxx5",
  "RequestId": "23781471-c213-44c5-92a4-731b882e25b5",
  "CiphertextBlob": "Rrnqz5fthTxcSdCYlw5pBoEWLvrdaqYNZ0oXK0mvYx/1Oo2R+DqEFPjji"
}
```

## Decryption Example

Now, let's decrypt the encrypted data, using the CMK created in the previous example as a reference.

### Input

```
tccli kms Decrypt --CiphertextBlob "Rrnqz5fthTxcSdCYlw5pBoEWLvrdaqYNZ0oXK0mvYx/1Oo2R+DqEFPjji"
```

### Output

If the execution is successful, the request data will return the Base64-encoded plaintext and the CMK ID used to encrypt the plaintext. Subsequently, an additional Base64 decryption operation is required to obtain the plaintext.

```
{
  "Plaintext": "VGhpcyBleGFtcGxlIGlzIHVzZWQgZm9yIHRlc3Rpbmc=",
  "KeyId": "6xxxxxx-xxxx-xxxx-xxxx-5xxxxxxxxxx5",
  "RequestId": "bcce3fae-**-**-d42780c10702"
}
```

# Asymmetric Key Decryption

Last updated: 2023-08-24 11:44:07

## Overview

KMS provides the following SM2 and RSA asymmetric key-based decryption APIs:

| API                  | API Description | Note   |
|----------------------|-----------------|--|
| AsymmetricSm2Decrypt | SM2 decryption  | Please refer to <a href="#">AsymmetricSm2Decrypt</a> |
| AsymmetricRsaDecrypt | RSA decryption  | Please refer to <a href="#">AsymmetricRsaDecrypt</a> |

This example uses Tencent Cloud's [Command Line Tool TCCLI](#). You can use any supported programming language for subsequent calls.

## Asymmetric Decryption

### RSA decryption

#### Input

```
tccli kms AsymmetricRsaDecrypt --KeyId 22d79428-61d9-11ea-a3c8-525400** --Algorith
```

#### Output

```
{
  "Response": {
    "RequestId": "6758cbf5-5e21-4c37-a2cf-8d47f5**",
    "KeyId": "22d79428-61d9-11ea-a3c8-525400**",
    "Plaintext": "dGVzdAo="
  }
}
```

### SM2 decryption

#### Input

```
tccli kms AsymmetricSm2Decrypt --KeyId 22d79428-61d9-11ea-a3c8-525400** --Ciphert
```

#### Output

```
{
  "Response": {
    "RequestId": "6758cbf5-5e21-4c37-a2cf-8d47f5**",
    "KeyId": "22d79428-61d9-11ea-a3c8-525400**",
    "Plaintext": "dGVzdAo="
  }
}
```

## View public key

### Overview

Obtain the public key information for the specified KeyId. For API documentation, please refer to [GetPublicKey](#).

This example uses Tencent Cloud's [Command Line Tool TCCLI](#). You can use any supported programming language for subsequent calls.

### Sample

#### Input

```
tccli kms GetPublicKey --KeyId 22d79428-61d9-11ea-a3c8-525400**
```

#### Output:

```
{
  "Response": {
    "RequestId": "408fa858-cd6d-4011-b8a0-653805**",
    "KeyId": "22d79428-61d9-11ea-a3c8-525400**",
    "PublicKey": "MIIBIjANBgkqhkiG9w0BAQEFAAOCAQ8AMIIBCgKCAQEAzQk7x7ladgVFE",
    "PublicKeyPem": "-----BEGIN PUBLIC KEY-----\nMIIBIjANBgkqhkiG9w0BAQEFAAOCAQ8/"
  }
}
```

# Deleting Key

Last updated: 2023-08-24 15:52:37

## Overview

The schedule key deletion feature involves the following two APIs:

| API                 | API Description                 | Note  |
|---------------------|---------------------------------|---|
| ScheduleKeyDeletion | Add scheduled key deletion task | The KeyId and PendingWindowInDays are mandatory parameters for this API operation. For more details, please refer to the <a href="#">ScheduleKeyDeletion</a> interface. |
| CancelKeyDeletion   | Cancel Scheduled Deletion Task  | The KeyId is a required parameter for this API operation. For more details, please refer to the <a href="#">CancelKeyDeletion</a> interface documentation.              |

### Note

If a CMK schedule deletion waiting period is set through the ScheduleKeyDeletion API when the CMK is in disabled status, the CMK will be deleted automatically at the specified time.

This example uses Tencent Cloud's [Command Line Tool TCCLI](#). You can use any supported programming language for subsequent calls.

## Sample

### Creating a scheduled deletion task example

This example shows you how to delete a disabled CMK in 7 days.

### Input

```
tccli kms ScheduleKeyDeletion --region ap-guangzhou --KeyId 5xxxxx-xxxx-xxxx-xxxx-52:
```

### Output

If the setting is successful, the ID of the CMK to be deleted and the schedule deletion timestamp will be returned.

```
{
```

```
"KeyId": "6xxxxxxx-xxxx-xxxx-xxxx-5xxxxxxxxxc09",  
"RequestId": "2bd72d85-f9dd-4465-ae51-beebff54f540",  
"DeletionDate": 1572512542  
}
```

## Canceling a scheduled deletion task example

This example shows you how to cancel a schedule deletion task, where the CMK is the one used in the above example.

### Input

```
tccli kms CancelKeyDeletion --region ap-guangzhou --KeyId 5xxxxx-xxxx-xxxx-xxxx-52xx:
```

### Output

If the execution is successful, the returned request will contain the ID of the CMK for which the schedule deletion task is successfully canceled.

```
{  
  "KeyId": "6xxxxxxx-xxxx-xxxx-xxxx-5xxxxxxxxxc09",  
  "RequestId": "c85473c6-e18d-4a09-9eac-03958dd4714d"  
}
```

# Archive Key

Last updated: 2023-08-24 15:53:11

## Overview

The operations of enabling and disabling key archiving involve the following two functions:

| API name          | API Description      | Note  |
|-------------------|----------------------|---|
| ArchiveKey        | Enable Key Archiving | The KeyId is a required parameter for this API operation. For more details, please refer to the <a href="#">ArchiveKey</a> interface documentation.       |
| CancelKey Archive | Unarchives keys      | The KeyId is a required parameter for this API operation. For more details, please refer to the <a href="#">CancelKeyArchive</a> interface documentation. |

This example uses Tencent Cloud's [Command Line Tool TCCLI](#). You can use any supported programming language for subsequent calls.

## Sample

### Enable Key Archiving

#### Input

```
tccli kms ArchiveKey --region ap-guangzhou --KeyId 5*-*-52*4
```

#### Output

If the key archiving is successfully enabled, the following request will be returned:

```
{
  "Response": {
    "RequestId": "1b580852-1e38-11e9-b129-5**19b4b00"
  }
}
```

### Unarchives keys

#### Input

```
tccli kms CancelKeyArchive --region ap-guangzhou --KeyId 5*-**---52*4
```

## Output

If the key archiving is successfully canceled, the following request will be returned:

```
{  
  "RequestId": "e5674638-1466-4607-a3ea-b**0f4e5e3"  
}
```