

Tencent Cloud Lighthouse Troubleshooting Product Documentation





Copyright Notice

©2013-2024 Tencent Cloud. All rights reserved.

Copyright in this document is exclusively owned by Tencent Cloud. You must not reproduce, modify, copy or distribute in any way, in whole or in part, the contents of this document without Tencent Cloud's the prior written consent.

Trademark Notice



All trademarks associated with Tencent Cloud and its services are owned by Tencent Cloud Computing (Beijing) Company Limited and its affiliated companies. Trademarks of third parties referred to in this document are owned by their respective proprietors.

Service Statement

This document is intended to provide users with general information about Tencent Cloud's products and services only and does not form part of Tencent Cloud's terms and conditions. Tencent Cloud's products or services are subject to change. Specific products and services and the standards applicable to them are exclusively provided for in Tencent Cloud's applicable terms and conditions.



Contents

Troubleshooting

"Remote Desktop Cannot Connect to the Remote Computer" Error Reported During Windows Instance Login




Troubleshooting

"Remote Desktop Cannot Connect to the Remote Computer" Error Reported During Windows Instance Login

Last updated: 2022-06-16 19:07:35

Symptom

When trying to connect to a Windows Lighthouse instance remotely on a local computer, you see the following error message:



Remote Desktop can't connect to the remote computer for one of these reasons:

- 1. Remote access to the server is not enabled
- 2. The remote computer is turned off
- 3. The remote computer is not available on the network

Make sure the remote computer is turned on and connected to the network, and that remote access is enabled.



Possible Cause

Possible causes include but are not limited to the following. Make analysis based on the actual situation.

The instance is in an abnormal status.

The remote login port (3389 by default) is not opened in the firewall of the instance.

Remote Desktop Services is not started.

There are issues with Remote Desktop settings.

There are issues with Windows Firewall settings.

Solutions


Troubleshoot the problems as instructed in Steps.

Steps

Checking if the instance is running

- 1. Log in to the Lighthouse console.
- 2. On the **Instances** page, check whether the instance is in **Running** status.






If yes, proceed to the next step.

If no, start the Windows instance.

Checking if port 3389 is opened

- 1. On the instance details page, select the **Firewall** tab.
- 2. Check whether the remote login port (3389 by default) is opened.





If yes, proceed to the next step.

If no, edit the firewall rules to open the port as instructed in Adding firewall rules.


Checking remote desktop service

1. Log in to the Windows instance via VNC and check whether the remote desktop service of the instance is enabled.

Note:


The following operations use an instance on Windows Server 2016 as an example.

2. Right-click



- 3. In the System pop-up window, select Advanced System Settings.
- 4. In the *System Properties* pop-up window, select the **Remote** tab and check whether the **Allow remote** connections to this computer is selected.





If yes, proceed to step 5.

If no, select it and click OK.


5.

Right-click



- 6. On the left sidebar in the **Computer Management** window, select **Services and Applications** > **Services**.
- 7. In the service list on the right, check whether *Remote Desktop Services is started.





If yes, proceed to step 8.

If no, start the service.


8.

Right-click



- 9. In the Run pop-up window, enter msconfig and click OK.
- 10. In the **System Configuration** pop-up window, check whether **Normal startup** is selected as shown below:





If yes, proceed to the next step.

If no, select it and click **OK**.

Checking Windows instance system settings

1. Log in to the Windows instance via VNC and check the system settings of the instance.

Note:


The following operations use an instance on Windows Server 2016 as an example.

2. Right-click



- 3. In the **Run** pop-up window, enter **services.msc** and press **Enter** to open the **Services** window.
- 4. Double-click to open the **Remote Desktop Services** properties and check whether **Remote Desktop Services** is running.





If yes, proceed to step 5.

If no, set Startup Type to Automatic and Service Status to Running (i.e., clicking Start).

5.


Right-click



6. In Control Panel, select System and Security > Windows Firewall.

7. In Windows Firewall, check the status of the Windows firewall.





If the status is **On**, proceed to step 8.


If the status is **Off**, toggle it on. If you can't turn it on, submit a ticket for assistance.

8.

In Windows Firewall

- , select Allow an app through Windows Firewall to open the Allowed apps window.
- 9. In the Allowed apps window, check whether Remote Desktop is selected in Allowed apps and features.





If yes, proceed to step 10.


If no, select **Remote Desktop** to allow it through Windows Firewall.

10.

In Windows Firewall

- , click Turn Windows Firewall on or off to open the Custom Settings window.
- 11. In the Custom Settings window, set Private network settings and Public network settings to Turn off Windows Firewall (not recommended).





If you still cannot connect to the Windows instance from the remote desktop, submit a ticket for assistance.