

# **Anti-DDoS Pro**

## **Getting Started**

### **Product Documentation**



## Copyright Notice

©2013-2024 Tencent Cloud. All rights reserved.

Copyright in this document is exclusively owned by Tencent Cloud. You must not reproduce, modify, copy or distribute in any way, in whole or in part, the contents of this document without Tencent Cloud's the prior written consent.

## Trademark Notice



All trademarks associated with Tencent Cloud and its services are owned by Tencent Cloud Computing (Beijing) Company Limited and its affiliated companies. Trademarks of third parties referred to in this document are owned by their respective proprietors.

## Service Statement

This document is intended to provide users with general information about Tencent Cloud's products and services only and does not form part of Tencent Cloud's terms and conditions. Tencent Cloud's products or services are subject to change. Specific products and services and the standards applicable to them are exclusively provided for in Tencent Cloud's applicable terms and conditions.

# Getting Started

Last updated : 2020-07-30 11:41:12

Anti-DDoS Pro provides Tencent Cloud public IPs with higher anti-DDoS capability. It supports Tencent Cloud services such as CVM, CLB, NAT, and WAF and is easy to access with no IP changes required. Currently, Anti-DDoS Pro offers two types of instances, single IP instances and multi-IP instances.

## Prerequisites

You need to purchase an Anti-DDoS Pro instance before you can bind it to the IP addresses you want to protect.

## Directions

1. Log in to the [Anti-DDoS Console](#) and go to **Anti-DDoS Pro > Resource List**.
  - For single IP instances, go to the **Single IP Instance** tab.
  - For multi-IP instances, go to the **Multi-IP Instance** tab.
2. Select the region of the target Anti-DDoS Pro instance and click **Bind Resource** in the "Operation" column to the right of the instance.
3. On the **Bind Resource** page, select **Resource Type** and **Resources to Associate** according to your needs.
  - A single IP instance can only be bound to one resource.
  - If your Anti-DDoS Pro instance is a multi-IP instance, you can select multiple options for **Resource Type** and **Resources to Associate**. The number of resources cannot exceed the **number of IPs** set when the instance is purchased.

Anti-DDoS Pro supports hosted IPs. This feature is currently made available through an allowlist. If you are using an IP hosted by Tencent Cloud and want to connect it to Anti-DDoS Pro, please call 95716 ext. 1 (9:00 AM–6:00 PM on business day) for consultation or [submit a ticket](#) for application.

4. Click **OK**.