

Tencent Cloud Automation Tools

Getting Started

Product Documentation



Copyright Notice

©2013-2024 Tencent Cloud. All rights reserved.

Copyright in this document is exclusively owned by Tencent Cloud. You must not reproduce, modify, copy or distribute in any way, in whole or in part, the contents of this document without Tencent Cloud's the prior written consent.

Trademark Notice



All trademarks associated with Tencent Cloud and its services are owned by Tencent Cloud Computing (Beijing) Company Limited and its affiliated companies. Trademarks of third parties referred to in this document are owned by their respective proprietors.

Service Statement

This document is intended to provide users with general information about Tencent Cloud's products and services only and does not form part of Tencent Cloud's terms and conditions. Tencent Cloud's products or services are subject to change. Specific products and services and the standards applicable to them are exclusively provided for in Tencent Cloud's applicable terms and conditions.

Getting Started

Last updated : 2022-05-23 15:27:20

TAT lets you manage Tencent Cloud services by using the console, API and SDK. This document guides you through the usage of TAT by taking Lighthouse console as an example.

Step 1. Installing TAT agent

Note:

TAT agent is pre-installed for instances created using public images after Dec 15, 2020. For instances created before this time, you need to install it manually.

TAT agent is only available for VPC-based instances.

See [Installing TAT Agent](#).

Step 2. Create a command

1. Log in to the Lighthouse console and select [My Commands](#) under **Automation Tools** on the left sidebar.
2. In the **My commands** page, click **Create command**.
3. Configure the parameters in the **Create command** page.

创建命令 ✕

命令名称

命令类型 SHELL POWERSHELL

执行路径

执行用户

超时时间 秒

请合理设置超时时间

命令内容

1

使用参数

保存命令
取消

Parameter	Description
Command name	Enter the command name.
Command type	Select a command type.
Execution path	Enter the execution path of the command. For Linux instances, the path defaults to the /home of the root account. For Windows instances, it defaults to C:\\\\Program Files\\\\qcloud\\\\tat_agent\\\\workdir of the System user
Execution user	The user who executes the command. For Linux instances, it defaults to the root user. For Windows instances, it defaults to the System user.
Timeout period	Set the timeout period of the command in the instance. When the task executing the command times out, the task process is terminated. It defaults to 60 seconds, and the range of values is [1, 86400].

Command content	Edit or paste your command.
Use parameters	Specify whether to use parameters in the command. You can configure the variable values in the command in the format of <code>{{key}}</code> .

4. Click **Save command** to complete the creation.

Step 3. Execute the command

Note: The target instance must be based on a VPC.

1. In the **My commands** page, select the target command and click **Execute**.
2. In the **Execute command** window, select the target instance.
3. Click **Execute command**.

After the task execution, you can check the task result in **My commands - Logs - Log details**.